Linux/UNIX IPC Programming

POSIX Shared Memory

Michael Kerrisk, man7.org © 2023

February 2023


mtk@man7.org

Outline	Rev: # e2bf8f005a44
13 POSIX Shared Memory	13-1
13.1 Overview	13-3
13.2 Creating and opening shared memory objects	13-8
13.3 Using shared memory objects	13-23
13.4 Synchronizing access to shared memory	13-32

Outline 13 POSIX Shared Memory 13-1 13.1 Overview 13-3 13.2 Creating and opening shared memory objects 13-8 13.3 Using shared memory objects 13-23 13.4 Synchronizing access to shared memory 13-32

Shared memory

- Data is exchanged by placing it in memory pages shared by multiple processes
 - Pages are in user virtual address space of each process



Shared memory

- Data transfer is not mediated by kernel
 - User-space copy makes data visible to other processes
 - → Very fast IPC
 - Compare with pipes and MQs:
 - Send requires copy from user to kernel memory
 - Receive requires copy from kernel to user memory
- But, need to synchronize access to shared memory
 - E.g., to prevent simultaneous updates
 - Commonly, semaphores are used

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-5 §13.1

POSIX shared memory objects

- Implemented (on Linux) as files in a dedicated tmpfs filesystem
 - tmpfs == virtual memory filesystem that employs swap space when needed
- Objects have kernel persistence
 - Objects exist until explicitly deleted, or system reboots
 - Can map an object, change its contents, and unmap
 - Changes will be visible to next process that maps object
- Accessibility: user/group owner + permission mask

POSIX shared memory APIs

- shm_open(): open existing shared memory (SHM) object/create and open new SHM object
 - Returns file descriptor that refers to open object
- ftruncate(): set size of SHM object
- mmap(): map SHM object into caller's address space
- close(): close file descriptor returned by shm_open()
- shm_unlink(): remove SHM object name, mark for deletion once all processes have closed
- munmap(): unmap SHM object (or part thereof) from caller's address space
- Compile with cc -lrt
 - (No longer needed since glibc 2.34)
- shm_overview(7) man page

Linux/UNIX IPC Programming ©2023, Michael Kerrisk POSIX Shared Memory 13-7 §13.1

Outline	
13 POSIX Shared Memory	13-1
13.1 Overview	13-3
13.2 Creating and opening shared memory objects	13-8
13.3 Using shared memory objects	13-23
13.4 Synchronizing access to shared memory	13-32

Creating/opening a shared memory object: shm_open()

- Creates and opens a new object, or opens an existing object
- name: name of object (/somename)
- Returns file descriptor on success, or −1 on error
 - This FD is used in subsequent APIs to refer to SHM
 - (The close-on-exec flag is automatically set for the FD)

[TLPI §54.2]

Creating/opening a shared memory object: shm_open()

oflag specifies flags controlling operation of call

- O_CREAT: create object if it does not already exist
- O_EXCL: (with O_CREAT) create object exclusively
 - Give error if object already exists
- O_RDONLY: open object for read-only access
- O_RDWR: open object for read-write access
 - NB: No O_WRONLY flag...
- O_TRUNC: truncate an existing object to zero length
 - Contents of existing object are destroyed

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-11 §13.2

Creating/opening a shared memory object: shm_open()

- mode: permission bits for new object
 - RWX for user / group / other
 - ANDed against complement of process umask
 - Required argument; specify as 0 if opening existing object

Sizing a shared memory object

- New SHM objects have length 0
- We must set size using ftruncate(fd, size)
 - Bytes in newly extended object are initialized to 0
 - If existing object is shrunk, truncated data is lost
 - Typically, ftruncate() is called before mmap()
 - But the calls can also be in the reverse order
- Can obtain size of existing object using fstat(fd, &statbuf)
 - st_size field of stat structure

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-13 §13.2

Mapping a shared memory object: mmap()

- Complex, general-purpose API for creating memory mapping in caller's virtual address space
 - 15+ bits employed in *flags*
 - See TLPI Ch. 49 and mmap(2)
- We consider only use with POSIX SHM
 - In practice, only a few decisions to make
 - Usually just length, prot, and maybe offset

Mapping a shared memory object: mmap()

- fd: file descriptor specifying object to map
 - Use FD returned by shm_open()
 - Note: once mmap() returns, fd can already be closed without affecting the mapping
- addr: address at which to place mapping in caller's virtual address space
 - Let's look at a picture...


Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-15 §13.2

Process memory layout (simplified)



Mapping a shared memory object: mmap()

- addr: address at which to place mapping in caller's virtual address space
 - But, this address may already be occupied
 - Therefore, kernel takes *addr* as only a **hint**
 - Ignored if address is already occupied
 - addr == NULL ⇒ let system choose address
 - Normally use NULL for POSIX SHM objects
- mmap() returns address actually used for mapping
 - Treat this like a normal C pointer
- On error, mmap() returns MAP_FAILED

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-17 §13.2

Mapping a shared memory object: mmap()

- length: size of mapping
 - Normally should be ≤ size of SHM object
 - System rounds up to multiple of system page size
 - sysconf(_SC_PAGESIZE)
- offset: starting point of mapping in underlying file or SHM object
 - Must be multiple of system page size
 - Commonly specified as 0 (map from start of object)

Mapping a shared memory object: mmap()

- prot: memory protections
 - ullet \Rightarrow set protection bits in page-table entries for mapping
 - (Protections can later be changed using *mprotect(2)*)
 - PROT_READ: for read-only mapping
 - PROT_READ | PROT_WRITE: for read-write mapping
 - Must be consistent with access mode of shm_open()
 - E.g., can't specify O_RDONLY to shm_open() and then PROT_READ | PROT_WRITE for mmap()
 - Also PROT_EXEC: contents of memory can be executed

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-19 §13.2

Mapping a shared memory object: mmap()

- flags: bit flags controlling behavior of call
 - POSIX SHM objects: need only MAP_SHARED
 - MAP_SHARED == make caller's modifications to mapped memory visible to other processes mapping same object

Example: pshm/pshm_create_simple.c

```
./pshm_create_simple /shm-object-name size
```

Create a SHM object with given name and size

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-21 §13.2

Example: pshm/pshm create simple.c

```
size_t size = atoi(argv[2]);
int fd = shm_open(argv[1], O_CREAT | O_EXCL | O_RDWR, S_IRUSR|S_IWUSR);
ftruncate(fd, size);
void *addr = mmap(NULL, size, PROT_READ | PROT_WRITE, MAP_SHARED, fd, 0);
```

- SHM object created with RW permission for user, opened with read-write access mode
- fd returned by shm_open() is used in ftruncate() + mmap()
- Same size is used in ftruncate() + mmap()
- mmap() not necessary, but demonstrates how it's done
- Mapping protections PROT_READ | PROT_WRITE consistent with O RDWR access mode

Outline	
13 POSIX Shared Memory	13-1
13.1 Overview	13-3
13.2 Creating and opening shared memory objects	13-8
13.3 Using shared memory objects	13-23
13.4 Synchronizing access to shared memory	13-32

Using shared memory objects

- Address returned by mmap() can be used just like any C pointer
 - Usual approach: treat as pointer to some structured type
- Can read and modify memory via pointer

[TLPI §48.6]

Example: pshm/pshm_write.c

```
./pshm_write /shm-name string
```

Open existing SHM object shm-name and copy string to it

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-25 §13.3

Example: pshm/pshm write.c

- Open existing SHM object
- Resize object to match length of command-line argument
- Map object at address chosen by system
- Copy argv[2] to object (without '\0')
- SHM object is closed and unmapped on process termination

Example: pshm/pshm_read.c

```
./pshm_read /shm-name
```

 Open existing SHM object shm-name and write the characters it contains to stdout

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-27 §13.3

Example: pshm/pshm_read.c

- Open existing SHM object
- Use fstat() to discover size of object
- Map the object, using size from fstat() (in sb.st_size)
- Write all bytes from object to stdout, followed by newline

Pointers in shared memory

A little care is required when storing pointers in SHM:

- Assuming we let system choose address at which to place SHM (as is recommended practice)
- ◆ SHM may be placed at different address in each process
- Suppose we want to build dynamic data structures, with pointers inside shared memory...
 - E.g., linked list
- Must use relative offsets, not absolute addresses
 - Absolute address has no meaning if mapping is at different location in another process

[TLPI §48.6]

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-29 §13.3


Pointers in shared memory

- Suppose we have situation at right
 - baseaddr is start of shared memory region
 - Want to store pointer to target in *p
- Wrong way:

• Correct method (relative offset):

To dereference "pointer":

```
target = baseaddr + *p;
```



The /dev/shm filesystem

On Linux:

- tmpfs filesystem used to implement POSIX SHM is mounted at /dev/shm
- Can list objects in directory with *ls(1)*
 - Is -I shows permissions, ownership, and size of each object

```
$ ls -l /dev/shm
-rw----. 1 mtk mtk 4096 Oct 27 13:58 myshm
-rw----. 1 mtk mtk 32 Oct 27 13:57 sem.mysem
```

- POSIX named semaphores are also visible in /dev/shm
 - As small SHM objects with names prefixed with "sem."
- Can delete objects with rm(1)

Linux/UNIX IPC Programming ©2023, Michael Kerrisk POSIX Shared Memory 13-31 §13.3

Outline		
13 POSIX Shared Memory	13-1	
13.1 Overview	13-3	
13.2 Creating and opening shared memory objects	13-8	
13.3 Using shared memory objects	13-23	
13.4 Synchronizing access to shared memory	13-32	

Synchronizing access to shared memory

- Accesses to SHM object by different processes must be synchronized
 - Prevent simultaneous updates
 - Prevent read of partially updated data
- Semaphores are a common technique
- POSIX unnamed semaphores are often convenient, since:
 - Semaphore can be placed inside shared memory region
 - (And thus, automatically shared)
 - We avoid task of creating name for semaphore

Synchronizing access to shared memory

- Other synchronization schemes are possible
 - E.g., if using SHM to transfer large data volumes:
 - Using semaphore pair to force alternating access is expensive (two context switches on each transfer!)
 - Divide SHM into (logically numbered) blocks
 - Use pair of pipes to exchange metadata about filled and emptied blocks (also integrates with poll()/epoll!)

 ${\sf Linux}/{\sf UNIX} \ {\sf IPC} \ {\sf Programming}$

©2023, Michael Kerrisk

POSIX Shared Memory

13-35 §13.4

Example: synchronizing with unnamed semaphores

- Example application maintains sequence number in SHM object
- Source files:
 - pshm/pshm_seqnum.h: defines structure stored in SHM object
 - pshm/pshm_seqnum_init.c:
 - Create and open SHM object
 - Initialize semaphore and (optionally) sequence number inside SHM object
 - pshm/pshm_seqnum_get.c: display current value of sequence number and (optionally) increase its value

Example: pshm/pshm_seqnum.h

- Header file used by pshm/pshm_seqnum_init.c and pshm/pshm_seqnum_get.c
- Includes headers needed by both programs
- Defines **structure used for SHM object**, containing:
 - Unnamed semaphore that guards access to sequence number
 - Sequence number

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-37 §13.4

Example: pshm/pshm_seqnum_init.c

```
./pshm_seqnum_init /shm-name [init-value]
```

- Create and open SHM object
- Reset semaphore inside object to 1 (i.e., semaphore available)
- Initialize sequence number

Example: pshm/pshm_seqnum_init.c

- Delete previous instance of SHM object, if it exists
- Create and open SHM object
- Use ftruncate() to adjust size of object to match structure
- Map object, using size of structure
- Initialize semaphore state to "available"
 - pshared specified as 1, for process sharing of semaphore
- o If argv[2] supplied, initialize sequence # to that value
 - Newly extended bytes of SHM object are initialized to 0

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-39 §13.4

Example: pshm/pshm_seqnum_get.c

```
./pshm_seqnum_get /shm-name [run-length]
```

- Open existing SHM object
- Fetch and display current value of sequence number in SHM object shm-name
- If run-length supplied, add to sequence number

Example: pshm/pshm_seqnum_get.c

- Open existing SHM object
- Map object, using size of shmbuf structure

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory


13-41 §13.4

Example: pshm/pshm_seqnum_get.c

- Reserve semaphore before touching sequence number
- Display current value of semaphore
- If (nonnegative) argv[2] provided, add to sequence number
 - Sleep during update, to see that other processes are blocked
- Release semaphore

Exercise

- Write two programs that exchange a stream of data of arbitrary length via a POSIX shared memory object [Shared header file: pshm/pshm_xfr.h]:
 - The "writer" creates and initializes the shared memory object and semaphores used by both programs, and then reads blocks of data from stdin and copies them a block at a time to the shared memory region
 Template: pshm/ex.pshm_xfr_writer.c].
 - The "reader" copies each block of data from the shared memory object to stdout [Template: pshm/ex.pshm_xfr_reader.c].



Note the following points:

• Use the structure defined in pshm/pshm_xfr.h for your shared memory.

[Exercise continues on next page]

Linux/UNIX IPC Programming


©2023, Michael Kerrisk

POSIX Shared Memory

13-43 §13.4

Exercise

• You must ensure that the writer and reader have **exclusive**, **alternating access** to the shared memory region (so that, for example, the writer does not copy new data into the region before the reader has copied the current data to **stdout**). The following diagram shows how two semaphores can be used to achieve this. The semaphores should be initialized as **wsem=1** and **rsem=0**, so that the writer has first access to the shared memory.



(The simplest approach is to use two **unnamed** semaphores stored inside the shared memory object; see the structure definition in pshm/pshm_xfr.h.) [Exercise continues on next page]

Exercise

- When the "writer" reaches end of file, it should provide an indication to the "reader" that there is no more data. To do this, maintain a byte-count field in the shared memory region which the "writer" uses to inform the "reader" how many bytes are to be written. Setting this count to 0 can be used to signal end-of-file. Once it has sent the last data block, the "writer" should unlink the shared memory object.
- Test your programs using a large file that contains random data:

```
$ dd if=/dev/urandom of=infile count=100000
$ ./ex.pshm_xfr_writer < infile &
$ ./ex.pshm_xfr_reader > outfile
$ diff infile outfile
```

There is also a target in the Makefile for performing this test:

```
make pshm_xfr_test
```

[An optional exercise follows on the next page]

Linux/UNIX IPC Programming

©2023, Michael Kerrisk

POSIX Shared Memory

13-45 §13.4

Exercise

2 Create a file of a suitable size (e.g., 512 MB in the following):

```
$ dd if=/dev/urandom of=/tmp/infile count=1000000
```

Then edit the BUF_SIZE value in the pshm/pshm_xfr.h header file to vary the value from 10'000 down to 10 in factors of 10, in each case measuring the time required for the reader to complete execution:

```
$ ./ex.pshm_xfr_writer < /tmp/infile &
$ time ./ex.pshm_xfr_reader > /dev/null
```

What is the reason for the variation in the time measurements?